







CV Pro – Troubleshooting





Error encountered: CV Pro unique ID fails to appear in the Wi-Fi list on your Windows OS.


Possible solution: Disable the firewall within Windows security and de-activate or turn-off the

Domain, Public and Private networks.

Error encountered: Receive a notification that the 'network security key

isn't correct.

Possible solution: Restart your computer and repeat the connection process. Re-enter the network security key as '12345678',







Error encountered: IPv4 address (192.168.4.2) is incorrect.

- Check your network properties in Wi-Fi settings.
- Verify if your computer is strictly connected as the second device.
- Disconnect the existing connection and try to re-connect by following the steps to establish connection between CV Pro kit and computer.





Error encountered: 'conda is not recognized as internal or external command, while executing the command 'my_conda'.

Possible solution: Check if you have installed, the 'miniconda' in the 'user profile path'.

```
C:\Users\User\Meritus-CVPRO-Windows\Meritus-CVPRO-main\Training_Process>my_conda
Hi! Please Ensure Internet Connection!
Give me a command - 'build' or 'activate' or 'deactivate': build
Creating a Virtual Environment:- cvpro ...
The system cannot find the path specified.
'conda' is not recognized as an internal or external command,
operable program or batch file.
Building the Environment...
Build failed.
```





Error encountered: 'Build failed'.

Possible solution: Re-enter the 'my_conda' command and then select the 'build' option.

```
Downloading and Extracting Packages:

Preparing transaction: done
Verifying transaction: done
Executing transaction: done
Executing transaction: done
ERROR conda.core.link:_execute(945): An error occurred while installing package 'defaults::vs2015_runtime-14.27.29016-h5e58377_2'.
Rolling back transaction: done

[Errno 13] Permission denied: 'C:\\Users\\robot\\miniconda3\\envs\\cvpro\\msvcp140.dll'
()

Suilding the Environment...
Build failed.

(base) C:\Users\robot\Meritus-CVPRO-Windows>
```





Error encountered: 'Installation failed', after entering the command, 'install_cvpro'.

Possible solution: Check if you have activated the environment using, 'build' option in the 'my_conda' command.

```
Type 'run_cvpro' to move the Bot around for Data-Collection Process.
Type 'train_cvpro' to train the Bot for Autonomous Process.
C:\Users\robot\Meritus-CVPRO-Windows>install cvpro
Do you have a valid Internet Connection? - 'y' or 'n': y
Installing dependencies.....
Requirement already satisfied: pip in c:\users\robot\miniconda3\envs\cvpro\lib\site-
Fatal error in launcher: Unable to create process using '"C:\Users\robot\AppData\Loc
Python310\Scripts\pip.exe" install tensorflow~=2.9.0': The system cannot find the fi
Fatal error in launcher: Unable to create process using '"C:\Users\robot\AppData\Loc
Python310\Scripts\pip.exe" install -r requirements.txt: The system cannot find the
Check for the following:
  Please ensure your Internet Connectivity is Stable.
  Please ensure you have activated the 'cvpro' Environment.
 Please ensure you have followed the execution steps in the order given.
C:\Users\robot\Meritus-CVPRO-Windows\Meritus-CVPRO-main\Environment    Setup>_
```





Error encountered: Installation of dependencies fails, after entering the command, 'install_cvpro'.

Possible solution: Follow the steps provided in the command instructions (highlighted in the given figure) and resolve the error. When resolved, re-enter the command, 'install cvpro'.

```
Internation of the two two managements of the content of the conte
```

When the installation process is complete, ensure to enter the command, '**pip list**' and verify the listed python library versions with the requirements.txt file, available in the '*%userProfile%\Meritus-CVPRO-Windows\Meritus-CVPRO-main\Environment_Setup*'.





Error encountered: Server fails to start and there is no progress beyond the line, 'mosquitto version 2.0.18 running'.

Possible solution:

Check your Windows Firewall setting. If it is enabled, disable the settings. Then close the command prompt, disconnect from your Wi-Fi network and restart the computer. When computer has restarted, follow the process described to initiate the server again.

```
MQTT Server

1713766802: mosquitto version 2.0.18 starting

1713766802: Config loaded from mqtt_conf.conf.

1713766802: Opening ipv4 listen socket on port 1883.

1713766802: mosquitto version 2.0.18 running
```





Error encountered: The requested address is not valid in its context.

- ✓ Check if IPv4 address is 192.168.4.2.
- ✓ Check if the CV Pro kit is connected with the computer.
- ✓ Check for order of connection, if it is followed (computer and then phone).
- ✓ Verify whether the appropriate CV Pro kit is linked to the computer. Ensure that both the unique ID of the CV Pro (e.g. cvpro101) and the SSID of your computer match precisely.

```
MQTT Server

1715064129: mosquitto version 2.0.18 starting

1715064129: Config loaded from mqtt_conf.conf.

1715064129: Opening ipv4 listen socket on port 1883.

1715064129: Error: The requested address is not valid in its context.

(cvpro) C:\Users\robot\Meritus-CVPRO-Windows\Meritus-CVPRO-main\Environment_Setup>
```





Error encountered (for windows OS): The system cannot find the path specified.

Possible solution: Check if you have installed the MQTT in C:\Program Files only.

```
MQTT Server
The system cannot find the path specified.

(cvpro) C:\Users\robot\Meritus-CVPRO-Windows\Meritus-CVPRO-main\Environment_Setup>_
```





Error encountered (for windows OS): Unable to open the config file 'mqtt_conf.conf'.

Possible solution: Check if the config file is found, only in '%userProfile%\Meritus-CVPRO-

Windows\Meritus-CVPRO-main\Environment_Setup'.

```
MQTT Server

1715065260: Error: Unable to open config file mqtt_conf.conf.

(cvpro) C:\Users\robot\Meritus-CVPRO-Windows\Meritus-CVPRO-main\Environment_Setup>
```





Error encountered (for macOS): 'Address already in use', when connecting with server using

`launch_server' command.

- o Check if you have already connected with the server and it is in use.
- Check if MQTT is auto-connected.
- o If either of the above is true, then close the MQTT server window (with error) and continue the process.

```
Last login: Tue May 7 12:18:49 on ttys000 printf "\e]1;MQTT Server\a"; mosquitto -v -c $HOME/Meritus-CVPRO-Mac/Meritus-CVPRO-main/Environment_Setup/mqtt_conf.conf rajkumarselvaraj@Apple ~ % printf "\e]1;MQTT Server\a"; mosquitto -v -c $HOME/Meritus-CVPRO-Mac/Meritus-CVPRO-main/Environment_Setup/mqtt_conf.conf 1715064560: mosquitto version 2.0.18 starting 1715064560: Config loaded from /Users/rajkumarselvaraj/Meritus-CVPRO-Mac/Meritus-CVPRO-main/Environment_Setup/mqtt_conf.conf. 1715064560: Opening ipv4 listen socket on port 1883. 1715064560: Error: Address already in use rajkumarselvaraj@Apple ~ %
```





Error encountered (for windowsOS): 'Only one usage of each socket address is normally permitted', when connecting with server using 'launch_server' command.

- o Check if you have already connected with the server and it is in use.
- Check if MQTT is auto-connected.
- o If either of the above is true, then close the MQTT server window (with error) and continue the process.

```
MQIT Server

1715066167: mosquitto version 2.0.18 starting
1715066167: Config loaded from mqtt_conf.conf.
1715066167: Opening ipv4 listen socket on port 1883.
1715066167: Error: Only one usage of each socket address (protocol/network address/port) is normally permitted.

C:\Users\robot\Meritus-CVPRO-Windows\Meritus-CVPRO-main\Environment_Setup>
```





Error encountered (for macOS): 'Command not found: mosquitto'.

Possible solution: Check if 'mosquitto' broker is installed in the 'user profile path' of your computer.

```
.4.2 scipy-1.13.0 seaborn-0.13.2 six-1.16.0 threadpoolctl-3.5.0 tqdm-4.66.2 tzda Last login: Thu May 2 10:23:05 on ttys006,
ta-2024.1 zipp-3.18.1
                                                                                  printf "\e]1;MQTT Server\a"; mosquitto -v -c $HOME/Meritus-CVPRO-Mac/Meritus-CVP
                                                                                  RO-main/Environment_Setup/mqtt_conf.conf
                                                                                  (base) ivanr@Ivans-MacBook-Pro ~ % printf "\e]1;MQTT Server\a"; mosquitto -v -c
Installation is Completed!
                                                                                  $HOME/Meritus-CVPRO-Mac/Meritus-CVPRO-main/Environment_Setup/mgtt_conf.conf
For Data Collection Process:
                                                                                  zsh: command not found: mosquitto
                                                                                  (base) ivanr@Ivans-MacBook-Pro ~ %
1. Please Disconnect the Internet, and connect the Bot with the System. Ensure t
he Connected IPv4 Address is: 192.168.4.2
2. Type 'launch_server' to Launch the MQTT Server to run the Bot!
3. Type 'run cypro' to begin the Data Collection Process!
For Training Process:

    Ensure your Bot is disconnected from the System as well as the Application.

2. Type 'train_cypro' to begin the Training Process!
[(cvpro) ivanr@Ivans-MacBook-Pro Environment_Setup % launch_server
tab 1 of window id 17954
(cvpro) ivanr@Ivans-MacBook-Pro Environment_Setup % launch_server
tab 1 of window id 17968
(cvpro) ivanr@Ivans-MacBook-Pro Environment_Setup %
```





Error encountered (for macOS): Command not found: mosquitto, even after installing mosquitto broker.

Possible solution: Check if mosquitto is installed in your computer, 'in the user profile path'.

```
Last login: Thu May 2 10:23:05 on ttys006
printf "\e]1;MQTT Server\a"; mosquitto -v -c $HOME/Meritus-CVPRO-Mac/Meritus-CVP
RO-main/Environment_Setup/mqtt_conf.conf
(base) ivanr@Ivans-MacBook-Pro ~ % printf "\e]1;MQTT Server\a"; mosquitto -v -c
$HOME/Meritus-CVPRO-Mac/Meritus-CVPRO-main/Environment_Setup/mqtt_conf.conf
zsh: command not found: mosquitto
[(base) ivanr@Ivans-MacBook-Pro ~ % mosquitto --version
zsh: command not found: mosquitto
[(base) ivanr@Ivans-MacBook-Pro ~ % mosquitto_sub --version
mosquitto_sub version 2.0.18 running on libmosquitto 2.0.18.
[(base) ivanr@Ivans-MacBook-Pro ~ % mosquitto_pub --version
mosquitto_pub version 2.0.18 running on libmosquitto 2.0.18.
((base) ivanr@Ivans-MacBook-Pro ~ %
```





Error encountered: 'Python not found', during data collection process. (when 'control' or 'videostream' option is given, under the command 'run_cvpro')

Possible solution: Check if you have activated the 'conda' environment.

```
Data Collection Process

Enter your choice - 'control' or 'videostream': control

Is your Bot connected with the Application? - 'y' or 'n': y

Running the Bot......

Python was not found; run without arguments to install from the Microsoft Store, or disable this shortcut from Settings > Manage App Execution Aliases.

Type 'run_cvpro' or 'train_cvpro' according to your requirement!

C:\Users\User\Meritus-CVPRO-Windows\Meritus-CVPRO-main\Controller>_
```





Error encountered: The CV Pro kit is not moving after entering the valid speed limit.

- 1. Check if the Python version is only 3.9.19, and also you have activated the 'conda' environment using the 'my_conda' command.
- 2. Enter the command, 'pip list' and verify the listed python library versions with the requirements.txt file, available in the '%userProfile%\Meritus-CVPRO-Windows\Meritus-CVPRO-main\Environment_Setup'.

```
Enter your choice - 'control' or 'videostream': control

Is your Bot connected with the Application? - 'y' or 'n': y

Running the Bot.....

pygame 2.4.0 (SDL 2.26.4, Python 3.9.19)

Hello from the pygame community. https://www.pygame.org/contribute.html

Enter a valid Speed Limit (170-255):220

Your Speed limit 122 --> 220
```





When you manually install, python libraries, (esp. 'paho-mqtt), you will encounter

Error encountered: 'Value Error: Unsupported callback API version'

Possible solution: Enter the command, 'pip list' and verify the listed python library versions with the requirements.txt file, available in the '%userProfile%\Meritus-CVPRO-Windows\Meritus-CVPRO-main\Environment_Setup'.

If any mismatch found, re-build the environment, using the build option in my_conda command and use install_cvpro command.

Refer to the image given in the next slide.









Error encountered: 'Python not found', during training process. (when 'train_cvpro' command is given)

Possible solution: Check if you have activated the 'conda' environment.





Error encountered: 'NotADirectoryError', during training process.

Possible solution:

> Check if no files, apart from the extracted zip file (data collected) are found in the given path -

%userProfile%\Meritus-CVPRO-Windows\Meritus-CVPRO-

main\Training_Process\Training_Data\Dataset_CVPRO\Autonomous_Driving\

For example the file can be - '20230920_110330'

Navigate to the same path and open command prompt, by giving 'cmd' in the address bar and delete the existing file by entering the command, 'del <filename.???> for example, 'del bash.txt'.

Refer to the image given in the next slide.





```
Deleting the Garbage Files, that are not required for Training Process......
Garbage Files are Deleted
Training Progress is Started....
Dataset_Folder : C:\Users\robot\Meritus-CVPRO-Windows\Meritus-CVPRO-main\Training_Process\Training_Data/Dataset_CVPRO\Autonomous_Driving
The Folder is not Present in List Folder
Dataset Folder : C:\Users\robot\Meritus-CVPRO-Windows\Meritus-CVPRO-main\Training Process\Training Data/Dataset CVPRO\Image Classification
                                                                                                                                                    | 0/1 [00:00<?, ?it/s]S
tatus : Current Directory -> C:\Users\robot\Meritus-CVPRO-Windows\Meritus-CVPRO-main\Training_Process\Training_Data/Dataset_CVPRO\Autonomous_Driving\20240215_124246\2024021
5 124232
CSV Length : 1233
Video length : 1118
The CSV length - 1233 is greater, so limiting no. of frames to video frame length count - 1118
Status : Writing images and csv to output folder ...
Status : Completed writing outputs ! for Dataset_CVPRO\Autonomous_Driving\20240215_124246\20240215_124232
                                                                                                                                            | 1/1 [00:08<00:00, 8.32s/it]
Data Pre-Processing Completed
Autonomous Driving
Folder_Path:C:\Users\robot\Meritus-CVPRO-Windows\Meritus-CVPRO-main\Training_Process\Training_Data/Dataset_CVPRO\Autonomous_Driving\20240215_124246\20240215_124232\Controls
CSV/Frame.csv
Traceback (most recent call last):
 File "C:\Users\robot\Meritus-CVPRO-Windows\Meritus-CVPRO-main\Training Process\main.pv", line 77, in <module>
   save df = preprocess.data frame()
  File "C:\Users\robot\Meritus-CVPRO-Windows\Meritus-CVPRO-main\Training Process\Utils\createdataset.py", line 261, in data frame
   self.autonomous_driving(self.root_folder, folder, save_df)
  File "C:\Users\robot\Meritus-CVPRO-Windows\Meritus-CVPRO-main\Training_Process\Utils\createdataset.py", line 238, in autonomous_driving
   for dataset folder in os.listdir(actual dataset path):
NotADirectoryError: [WinError 267] The directory name is invalid: 'C:\\Users\\robot\\Meritus-CVPRO-Windows\\Meritus-CVPRO-main\\Training Process\\Training Data/Dataset CVPR
O\\Autonomous Driving\\bash.txt'
```





Error encountered: 'ModuleNotFoundError: No module named 'pygame", during data collection or training process.

Possible solution: Check if you have successfully installed the python libraries using the command,

'install_cvpro'.

```
your Bot Disconnected from the Application and System? - 'v' or 'n': v
ve me a valid Batch Size [16, 32, 64, 128]:
Batch Size: 32
ve me a valid Epoch Value [5, 10, 20, 25, 50, 100]
Epoch Value: 5
ve me a valid Learning Rate [0.00001, 0.0001, 0.001, 0.01, 0.1, 1]:
 Learning Rate: 0.0001
eleting the Garbage Files, that are not required for Training Process.....
rbage Files are Deleted
aceback (most recent call last):
File "C:\Users\robot\Meritus-CVPRO-Windows\Meritus-CVPRO-main\Training_Process\main.py", line 23, in <module>
 from Utils.createdataset import CreateDataset
File "C:\Users\robot\Meritus-CVPRO-Windows\Meritus-CVPRO-main\Training_Process\Utils\createdataset.py", line 15, in <module:
 import cv2
duleNotFoundError: No module named 'cv2'
vpro) C:\Users\robot\Meritus-CVPRO-Windows\Meritus-CVPRO-main\Training_Process>_
```

```
Enter your choice - 'control' or 'videostream': control
Is your Bot connected with the Application? - 'y' or 'n': y
Running the Bot.....
Traceback (most recent call last):
File "C:\Users\robot\Meritus-CVPRO-Windows\Meritus-CVPRO-main\Controller\control_bot.py", line 25, in <module>
import pygame
ModuleNotFoundError: No module named 'pygame'

Type 'run_cvpro' or 'train_cvpro' according to your requirement!

(cvpro) C:\Users\robot\Meritus-CVPRO-Windows\Meritus-CVPRO-main\Controller>_
```